NAME

How to build fstrcmp

SPACE REQUIREMENTS

You will need about 3MB to unpack and build the *fstrcmp* package. Your milage may vary.

BEFORE YOU START

There are a few pieces of software you may want to fetch and install before you proceed with your installation of fstrcmp

GNU libtool
: The libtool program is used to build shared libraries. It understands neccesary weird and wonderful compiler and linker tricks on many weird and wonderful systems.
http://www.gnu.org/software/libtool/

GNU Groff
: The documentation for the *fstrcmp* package was prepared using the GNU Groff package (version 1.14 or later). This distribution includes full documentation, which may be processed into PostScript or DVI files at install time – if GNU Groff has been installed.

GCC
: You may also want to consider fetching and installing the GNU C Compiler if you have not done so already. This is not essential. The fstrcmp program was developed using the GNU C compiler.

The GNU FTP archives may be found at `ftp.gnu.org`, and are mirrored around the world.

SITE CONFIGURATION

The **fstrcmp** package is configured using the *configure* program included in the source distribution.

The *configure* shell script attempts to guess correct values for various system-dependent variables used during compilation, and creates the *Makefile* and *lib/config.h* files. It also creates a shell script *config.status* that you can run in the future to recreate the current configuration.

Normally, you just *cd* to the directory containing *fstrcmp*'s source code and then type

```
% ./configure
...lots of output...
%
```

If you're using *csh* on an old version of System V, you might need to type

```
% sh configure
...lots of output...
%
```

instead, to prevent *csh* from trying to execute *configure* itself.

Running *configure* takes a minute or two. While it is running, it prints some messages that tell what it is doing. If you don't want to see the messages, run *configure* using the quiet option; for example,

```
% ./configure --quiet
%
```

To compile the **fstrcmp** package in a different directory from the one containing the source code, you must use a version of *make* that supports the *VPATH* variable, such as *GNU make*. Then *cd* to the directory where you want the object files and executables to go and run the *configure* script. The *configure* script automatically checks for the source code in the directory that *configure* is in and in .. (the parent directory). If for some reason *configure* is not in the source code directory that you are configuring, then it will report that it can't find the source code. In that case, run *configure* with the option `--srcdir=`*DIR*, where *DIR* is the directory that contains the source code.

By default, *configure* will arrange for the *make install* command to install the **fstrcmp** package's files in */usr/local/bin*, */usr/local/lib*, */usr/local/include*, and */usr/local/man*. There are options which allow you to control the placement of these files.

`--prefix=`*PATH*
: This specifies the path prefix to be used in the installation. Defaults to */usr/local* unless otherwise specified.

`--exec-prefix=`*PATH*
: You can specify separate installation prefixes for architecture-specific files files. Defaults to *${prefix}* unless otherwise specified.

`--bindir=`*PATH*
: This directory contains executable programs. On a network, this directory may be shared between machines with identical hardware and operating systems; it may be mounted read-only. Defaults to *${exec_prefix}/bin* unless otherwise specified.

`--mandir=`*PATH*
: This directory contains the on-line manual entries. On a network, this directory may be shared between all machines; it may be mounted read-only. Defaults to *${prefix}/man* unless otherwise specified.

The *configure* script ignores most other arguments that you give it; use the `--help` option for a complete list.

On systems that require unusual options for compilation or linking that the *fstrcmp* package's *configure* script does not know about, you can give *configure* initial values for variables by setting them in the environment. In Bourne-compatible shells, you can do that on the command line like this:

```
$ CXX='gcc -traditional' LIBS=-lposix ./configure
...lots of output...
$
```

Here are the *make* variables that you might want to override with environment variables when running the *configure* script:

Variable: CC
: C compiler program. The default is *cc*.

Variable: CPPFLAGS
: Preprocessor flags, commonly defines and include search paths. Defaults to empty. It is common to use `CPPFLAGS=-I/usr/local/include` to access other installed packages.

Variable: INSTALL
: Program to use to install files. The default is *install* if you have it, *cp* otherwise.

Variable: LIBS
: Libraries to link with, in the form `-l`*foo* `-l`*bar*. The *configure* script will append to this, rather than replace it. It is common to use `LIBS=-L/usr/local/lib` to access other installed packages.

If you need to do unusual things to compile the package, the author encourages you to figure out how the *configure* script could check whether to do them, and mail diffs or instructions to the author so that they can be included in the next release.

BUILDING FSTRCMP

All you should need to do is use the

```
% make
...lots of output...
%
```

command and wait.

You can remove the program binaries and object files from the source directory by using the

```
% make clean
...lots of output...
%
```

command. To remove all of the above files, and also remove the *Makefile* and *lib/config.h* and *config.status* files, use the

```
% make distclean
...lots of output...
%
```

command.

The file *etc/configure.ac* is used to create *configure* by a GNU program called *autoconf*. You only need to know this if you want to regenerate *configure* using a newer version of *autoconf*.

TESTING FSTRCMP

The *fstrcmp* package comes with a test suite. To run this test suite, use the command

```
% make sure
...lots of output...
Passed All Tests
%
```

The tests take a fraction of a second each, with most very fast, and a couple very slow, but it varies greatly depending on your CPU.

If all went well, the message

```
Passed All Tests
```

should appear at the end of the make.

INSTALLING FSTRCMP

As explained in the *SITE CONFIGURATION* section, above, the *fstrcmp* package is installed under the */usr/local* tree by default. Use the `--prefix=`*PATH* option to *configure* if you want some other path. More specific installation locations are assignable, use the `--help` option to the *configure* script for details.

All that is required to install the *fstrcmp* package is to use the

```
% make install
...lots of output...
%
```

command. Control of the directories used may be found in the first few lines of the *Makefile* file and the other files written by the *configure* script; it is best to reconfigure using the *configure* script, rather than attempting to do this by hand.

GETTING HELP

If you need assistance with the *fstrcmp* package, please do not hesitate to contact the author at

```
Peter Miller <pmiller@opensource.org.au>
```

Any and all feedback is welcome.

When reporting problems, please include the version number given by the

```
% explain -version
explain version 0.7.D001
...warranty disclaimer...
%
```

command. Please do not send this example; run the program for the exact version number.

COPYRIGHT

fstrcmp version 0.7
Copyright © 2009 Peter Miller
Peter Miller <pmiller@opensource.org.au>

The comparison code is derived from the fuzzy comparison functions in GNU Gettext 0.17. The GNU Gettext comparison functions were, in turn, derived from GNU Diff 2.7.

Copyright © 1988-2009 Free Software Foundation

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program. If not, see <http://www.gnu.org/licenses/>.

It should be in the *LICENSE* file included in the source distribution.